



DECUS

PROGRAM LIBRARY

DECUS NO.	8-289
TITLE	"ULKA" THE ULTIMATE KALEIDOSCOPE
AUTHOR	Dr. A. S. French
COMPANY	University of Alberta Edmonton, Alberta, Canada
DATE	September 9, 1970
SOURCE LANGUAGE	PAL-D

ATTENTION

This is a USER program. Other than requiring that it conform to submittal and review standards, no quality control has been imposed upon this program by DECUS.

The DECUS Program Library is a clearing house only; it does not generate or test programs. No warranty, express or implied, is made by the contributor, Digital Equipment Computer Users Society or Digital Equipment Corporation as to the accuracy or functioning of the program or related material, and no responsibility is assumed by these parties in connection therewith.

DECUS

PROGRAM LIBRARY



THE UNIVERSITY OF CHICAGO

LIBRARY

CHICAGO, ILL.

6060 S. UNIVERSITY AVE.

CHICAGO, ILL. 60637

UNIVERSITY OF CHICAGO

THE UNIVERSITY OF CHICAGO LIBRARY
6060 S. UNIVERSITY AVE. CHICAGO, ILL. 60637

THE UNIVERSITY OF CHICAGO LIBRARY
6060 S. UNIVERSITY AVE. CHICAGO, ILL. 60637
UNIVERSITY OF CHICAGO LIBRARY
6060 S. UNIVERSITY AVE. CHICAGO, ILL. 60637

"ULKA" THE ULTIMATE KALEIDOSCOPE PROGRAM

DECUS Program Library Write-up

DECUS No. 8-289

ABSTRACT

"ULKA" is a true kaleidoscope program for use on the LAB-8 Computer. Unlike other kaleidoscope programs "ULKA" is completely automatic, no user interaction being required to produce a dazzling array of patterns.

LOADING

"ULKA" may be loaded with the Binary Loader or with the System Loader if using the Disk Monitor System. The program starts at location 200 and after starting runs automatically until stopped. If the Disk Monitor System is in use striking Control/C will cause a return to monitor.

OPERATION

"ULKA" starts at a random point in its repertoire of more than sixteen million patterns and continues displaying patterns at random at a rate which is determined by the speed of the RC Clock in the AX08 Lab Peripheral. The RC Clock should be adjusted using the two controls on the front panel of the AX08 until the display is suitable.

ACC	0053
BRIGHT	6326
CIRCLE	0305
CLEAR	6357
CLOCK	0033
CLRK	6354
CYCLE	0265
DISPLA	0302
ENABLE	6346
END	0042
GARB	0225
GARB1	0350
GARB2	0351
KEY	0045
KOUNT	0347
KOUNTR	0044
LINK	0054
PATT	0262
SHOW	0317
SKRK	6341
SKXK	6321
SWITCH	0352
TEMP	0353
ULKA	0200

XLIST
 /ULKA-THE ULTIMATE KALEIDOSCOPE.
 /LAB-8 COMPUTER ONLY.
 /START AT 200 USES INTERRUPT.
 /SAVE ULKA:0-377;200(CR).

0200	6032	ULKA,
0201	6601	
0202	6042	
0203	6326	
0204	6357	
0205	6022	
0206	2347	
0207	7000	
0210	6321	
0211	5206	
0212	1347	
0213	3350	
0214	1350	
0215	7040	
0216	7012	
0217	3351	

*200
 KCC
 DCMA
 TCF
 BRIGHT
 CLEAR
 PCF
 ISZ KOUNT
 NOP
 SKXK
 JMP .-3
 TAD KOUNT
 DCA GARB1
 TAD GARB1
 CMA
 RTR
 DCA GARB2

Ø220	1377		TAD (1ØØ2
Ø221	6346		ENABLE
Ø222	6ØØ1		ION
Ø223	4225		JMS GARB
Ø224	5223		JMP .-1
Ø225	ØØØØ	GARB,	Ø
Ø226	4262		JMS PATT
Ø227	135Ø		TAD GARB1
Ø23Ø	Ø376		AND (77
Ø231	71Ø6		CLL RTL
Ø232	7ØØ6		RTL
Ø233	7ØØ6		RTL
Ø234	3353		DCA TEMP
Ø235	135Ø		TAD GARB1
Ø236	Ø375		AND (77ØØ
Ø237	7112		CLL RTR
Ø24Ø	7Ø12		RTR
Ø241	7Ø12		RTR
Ø242	1353		TAD TEMP
Ø243	335Ø		DCA GARB1
Ø244	1351		TAD GARB2
Ø245	Ø376		AND (77
Ø246	71Ø6		CLL RTL
Ø247	7ØØ6		RTL
Ø25Ø	7ØØ6		RTL
Ø251	3353		DCA TEMP
Ø252	1351		TAD GARB2
Ø253	Ø375		AND (77ØØ
Ø254	7112		CLL RTR
Ø255	7Ø12		RTR
Ø256	7Ø12		RTR
Ø257	1353		TAD TEMP
Ø26Ø	3351		DCA GARB2
Ø261	5625		JMP I GARB
Ø262	ØØØØ	PATT,	Ø
Ø263	1374		TAD (-15
Ø264	3347		DCA KOUNT
Ø265	135Ø	CYCLE,	TAD GARB1
Ø266	71Ø4		CLL RTL
Ø267	72ØØ		CLA
Ø27Ø	1351		TAD GARB2
Ø271	7ØØ4		RTL
Ø272	3351		DCA GARB2
Ø273	135Ø		TAD GARB1
Ø274	7ØØ4		RTL
Ø275	335Ø		DCA GARB1
Ø276	43Ø2		JMS DISPLA
Ø277	2347		ISZ KOUNT
Ø3ØØ	5265		JMP CYCLE
Ø3Ø1	5662		JMP I PATT

Ø3Ø2	ØØØØ	DISPLA,	Ø
Ø3Ø3	724Ø		CLA CMA
Ø3Ø4	3352		DCA SWITCH
Ø3Ø5	4317	CIRCLE,	JMS SHOW
Ø3Ø6	135Ø		TAD GARBI
Ø3Ø7	3353		DCA TEMP
Ø31Ø	1351		TAD GARB2
Ø311	335Ø		DCA GARBI
Ø312	1353		TAD TEMP
Ø313	3351		DCA GARB2
Ø314	2352		ISZ SWITCH
Ø315	57Ø2		JMP I DISPLA
Ø316	53Ø5		JMP CIRCLE
Ø317	ØØØØ	SHOW,	Ø
Ø32Ø	135Ø		TAD GARBI
Ø321	1373		TAD (377
Ø322	63Ø3		63Ø3
Ø323	72ØØ		CLA
Ø324	1351		TAD GARB2
Ø325	1372		TAD (-377
Ø326	6317		6317
Ø327	72ØØ		CLA
Ø33Ø	135Ø		TAD GARBI
Ø331	7Ø41		CIA
Ø332	1373		TAD (377
Ø333	63Ø7		63Ø7
Ø334	72ØØ		CLA
Ø335	1351		TAD GARB2
Ø336	7Ø41		CIA
Ø337	1372		TAD (-377
Ø34Ø	6317		6317
Ø341	72ØØ		CLA
Ø342	135Ø		TAD GARBI
Ø343	1373		TAD (377
Ø344	63Ø7		63Ø7
Ø345	72ØØ		CLA
Ø346	5717		JMP I SHOW
Ø347	ØØØØ	KOUNT,	Ø
Ø35Ø	2525	GARB1,	2525
Ø351	5252	GARB2,	5252
Ø352	ØØØØ	SWITCH,	Ø
Ø353	ØØØØ	TEMP,	Ø
Ø372	74Ø1		
Ø373	Ø377		
Ø374	7763		
Ø375	77ØØ		
Ø376	ØØ77		
Ø377	1ØØ2		

0000	0000		*0
0001	3053		0
0002	7004		DCA ACC
0003	3054		RAL
0004	5020		DCA LINK
			JMP 20
			*20
0020	6341		SKRK
0021	7410		SKP
0022	4033		JMS CLOCK
0023	6031		KSF
0024	7410		SKP
0025	4045		JMS KEY
0026	1054		TAD LINK
0027	7010		RAR
0030	1053		TAD ACC
0031	6001		ION
0032	5400		JMP I 0
0033	0000	CLOCK,	0
0034	6354		CLRK
0035	2044		ISZ KOUNTR
0036	5433		JMP I CLOCK
0037	2777		ISZ GARB1
0040	7410		SKP
0041	2776		ISZ GARB2
0042	7300	END,	CLA CLL
0043	5433		JMP I CLOCK
0044	0000	KOUNTR,	0
0045	0000	KEY,	0
0046	6036		KRB
0047	1175		TAD (-203
0050	7650		SNA CLA
0051	5574		JMP I (7600
0052	5445		JMP I KEY
0053	0000	ACC,	0
0054	0000	LINK,	0
0174	7600		
0175	7575		
0176	0351		
0177	0350		

